

# i want to disable all ModSecurity Rule in centos?

Topics : [Centos Server](#)

Written on [September 07, 2024](#)

To disable all **ModSecurity** rules on CentOS, you can either disable the entire ModSecurity engine or turn off the rules globally for your web server (Apache or Nginx). Here's how to disable all rules in ModSecurity:

## For Apache

### 1. Open ModSecurity Configuration File

The ModSecurity configuration file for Apache is usually located at:

```
/etc/httpd/conf.d/mod_security.conf
```

or

```
/etc/modsecurity/modsecurity.conf
```

### 2. Disable ModSecurity Engine Globally

Open the file in a text editor (e.g., nano or vi):

```
sudo nano /etc/httpd/conf.d/mod_security.conf
```

Find the line that reads:

```
SecRuleEngine On
```

Change it to:

```
SecRuleEngine Off
```

This will disable all ModSecurity rules.

### 3. Restart Apache

After making changes, restart the Apache service to apply the new settings:

```
sudo systemctl restart httpd
```

## For Nginx

### 1. Open ModSecurity Configuration File

For Nginx, the ModSecurity configuration file is typically located at:

```
/etc/nginx/modsec/modsecurity.conf
```

### 2. Disable ModSecurity Engine

Open the configuration file:

```
sudo nano /etc/nginx/modsec/modsecurity.conf
```

Find the following line:

```
SecRuleEngine On
```

Change it to:

```
SecRuleEngine Off
```

This will disable all ModSecurity rules for Nginx.

### 3. Restart Nginx

Restart Nginx to apply the changes:

```
sudo systemctl restart nginx
```

## Optional: Disable ModSecurity Completely

If you want to **completely disable ModSecurity** (not just the rules) on Apache or Nginx, you can comment out or remove the ModSecurity module loading line from the server's configuration:

### For Apache

1. **Open the main Apache configuration file** (typically `/etc/httpd/conf/httpd.conf` or

```
/etc/httpd/conf.modules.d/00-base.conf).
```

**2. Comment out the ModSecurity module loading line:**

```
# LoadModule security2_module modules/mod_security2.so
```

**3. Restart Apache:**

```
sudo systemctl restart httpd
```

**For Nginx**

**1. Open the Nginx configuration file** (typically /etc/nginx/nginx.conf).

**2. Comment out or remove the ModSecurity module loading line:**

```
# load_module modules/nginx_http_modsecurity_module.so;
```

**3. Restart Nginx:**

```
sudo systemctl restart nginx
```

By following these steps, you can effectively disable all ModSecurity rules or the entire ModSecurity engine on your CentOS server. Let me know if you encounter any issues or need further assistance!

© Copyright **Aryatechno**. All Rights Reserved. Written tutorials and materials by [Aryatechno](#)